



Site: Haymarket, Teddington Studios

Date: November 2013

Surveyor: H. Appleyard

Ref: ts3/haymarket

Tree No.	English Name	Height	Crown Spread	Ground Clearance	Age Class	Stem Diameter	Protection Multiplier	Protection Radius	Growth Vitality	Structural Condition	Landscape Contribution	B.S. Cat	Sub Cat	Useful Life	Observations
T1	Chestnut, Horse	12	5 4 5 4	3	Mature	570	12	6.8	Normal	Fair	Medium	C	1,2	10-20	Pollard (Old) Some 'Bleeding Canker' Entry wounds at base, flush cuts, decay in knuckles
T2	Chestnut, Horse	21	9 7 6 6	3	Mature	1080	12	13.0	Normal	Fair	Medium	B	2	20-40	Low branches Decay at trunk base & upper crown Historic root wounds, co-linked decay at multiple pruning sites
T3	Lime, Common	12	6 6 4 5	2.5	Mature	570	12	6.8	Normal	Fair	Medium	B	2	20-40	Decay in wound/cavity in base Stubs and snags Epicormic growth; extending over light
T4	Pine- Corsican	12	4 5 3 5	6	Mature	490	12	5.9	Normal	Fair	High	B	1,2	20-40	Deadwood throughout crown Resin bleeding historic impact wounds
T5	Tree of Heaven	10	6 4 4 4	1	Mature	540	12	6.5	Normal	Good	High	B	2	20-40	Dense canopy Root pattern affected by structures Canopy Extending over light and car park
T6	Oak, Common	8	5 7 5 7	2	Middle Aged	390	12	4.7	Normal	Good	Medium	B	1,2	20-40	Stubs and snags Touching street lamp

Notes:

1. Height describes the approximate height of the tree in meters from ground level.
2. The Crown Spread refers to the crown radius in meters from the stem centre and is shown above on each of the four compass points (i.e. N, E, S, W) clockwise.
3. Ground Clearance is the height in meters of crown clearance above adjacent ground level.
4. Stem Diameter is the diameter of the stem measured in millimetres at 1.5m from ground level or just above ground level for multi stemmed trees. The diameter may be estimated (e), where access is restricted. An average (a) may be taken for tree groups. A full inspection is always recommended.
5. Protection Multiplier is 12 for single stemmed and 10 for multi-stemmed trees.

6. Protection Radius is a radial distance measured from the trunk centre and is used to calculate the BS RPA.
7. Growth Vitality - Normal growth, Moderate (below normal), Poor (sparse/weak), Dead (dead or dying tree).
8. Structural Condition - Good (no or only minor defects), Fair (remediable defects), Poor - Major defects present or suspected.
9. Landscape Contribution - High (prominent landscape feature), Medium (visible in landscape), Low (secluded/among other trees).
10. B.S. Cat. refers to British Standard 5837:2005 Table 1 category and refers to tree/group quality and value; 'A' - High, 'B' - Moderate, 'C' - Low, 'R' - Remove or very poor quality.
11. Sub Cat refers to the retention criteria values where 1 is Arboricultural, 2 is Landscape and 3 is Cultural including Conservation/ecological, historic and commemorative.
12. Useful Life is the tree's estimated remaining effective contribution in years.

Site: Haymarket, Teddington Studios

Date: November 2013

Surveyor: H. Appleyard

Ref: ts3/haymarket

Tree No.	English Name	Height	Crown Spread	Ground Clearance	Age Class	Stem Diameter	Protection Multiplier	Protection Radius	Growth Vitality	Structural Condition	Landscape Contribution	B.S. Cat	Sub Cat	Useful Life	Observations
T7	Tree of Heaven	16	12 12 11 11	2	Over-Mature	900e	12	10.8	Normal	Fair	High	B	2	20-40	Inspection limited by ivy Deadwood throughout crown Historic impact damage to roots
G8	Eucalyptus, Honey Locust; Cotoneaster	8	3 3 3 2	1.5	Middle Aged	300a	12	3.6	Normal	Fair	Medium	B	2	20-40	Boundary screen tree Ornamental boundary trees Extending over car park and river
T9	Lime, Common	12	8 6 6 5	2	Mature	740	12	8.9	Normal	Poor	Medium	C	1	20-40	Pollard (Old) Extensive decay in cavity Epicormic growth; wound wood surrounding open cavity;
T10	Horse Chestnut	18	9 7 9 7	2.5	Over-Mature	1350e	10	13.5	Moderate	Poor	High	C	2	10-20	Multi stem weakness Reduced in past Decay in primary limb west, Included bark in stem unions, multiple decay points within crown
T11	Robinia(False Acacia)	21	6 6 7 7	7	Mature	900e	12	10.8	Normal	Fair	Medium	C	1,2	20-40	Off-site tree Broken & split branches Decay in over-hanging branches;
T11.1	Chestnut, Horse	20	4 6 6 5	3	Mature	1100e	10	11.0	Normal	Good	High	B	1,2	>40	Off-site tree Root pattern affected by structures Roots likely to be predominantly off-site; old pruning wounds in branches

Notes:

1. Height describes the approximate height of the tree in meters from ground level.
2. The Crown Spread refers to the crown radius in meters from the stem centre and is shown above on each of the four compass points (i.e. N, E, S, W) clockwise.
3. Ground Clearance is the height in meters of crown clearance above adjacent ground level.
4. Stem Diameter is the diameter of the stem measured in millimetres at 1.5m from ground level or just above ground level for multi stemmed trees. The diameter may be estimated (e), where access is restricted. An average (a) may be taken for tree groups. A full inspection is always recommended.
5. Protection Multiplier is 12 for single stemmed and 10 for multi-stemmed trees.

6. Protection Radius is a radial distance measured from the trunk centre and is used to calculate the BS RPA.
7. Growth Vitality - Normal growth, Moderate (below normal), Poor (sparse/weak), Dead (dead or dying tree).
8. Structural Condition - Good (no or only minor defects), Fair (remediable defects), Poor - Major defects present or suspected.
9. Landscape Contribution - High (prominent landscape feature), Medium (visible in landscape), Low (secluded/among other trees).
10. B.S. Cat. refers to British Standard 5837:2005 Table 1 category and refers to tree/group quality and value; 'A' - High, 'B' - Moderate, 'C' - Low, 'R' - Remove or very poor quality.
11. Sub Cat refers to the retention criteria values where 1 is Arboricultural, 2 is Landscape and 3 is Cultural including Conservation/ecological, historic and commemorative.
12. Useful Life is the tree's estimated remaining effective contribution in years.

Site: Haymarket, Teddington Studios

Date: November 2013

Surveyor: H. Appleyard

Ref: ts3/haymarket

Tree No.	English Name	Height	Crown Spread	Ground Clearance	Age Class	Stem Diameter	Protection Multiplier	Protection Radius	Growth Vitality	Structural Condition	Landscape Contribution	B.S. Cat	Sub Cat	Useful Life	Observations
G11.2	Holly/Ash/Horse Chestnut group	14	3 3 4 2	4	Mature	400e	12	4.8	Normal	Good	Medium	B	1,2	20-40	Boundary tree (group) Off-site trees Roots confined to neighbouring land
G12	Tree of Heaven	8	3 2 3 3	2.5/N2	Young	200	12	2.4	Normal	Good	Medium	C	1,2	20-40	Wrong location (best removed) Self sown
T13	Chestnut, Horse	12	6 5 5 5	3/W4	Mature	550	12	6.6	Normal	Fair	Medium	B	1,2	20-40	Root pattern affected by structures Bark wounds (decay entry point) at trunk base
T14	Hornbeam	8	2 2 2 2	2/N2	Young	190	12	2.3	Normal	Good	Medium	B	1,2	>40	A tree with insignificant defects Dense canopy
T15	Apple, Crab	5	2 3 3 2	1.5/S2	Middle Aged	150	12	1.8	Normal	Good	Low	C	1,2	10-20	Garden ornamental Root pattern affected by structures
T16	Box Elder	8	3 3 3 3	2/W2	Mature	230	12	2.8	Moderate	Fair	Low	C	1,2	10-20	Dying back Stubs and snags Dead wood through out the crown; appears stressed; roots confined to planter

Notes:

1. Height describes the approximate height of the tree in meters from ground level.
2. The Crown Spread refers to the crown radius in meters from the stem centre and is shown above on each of the four compass points (i.e. N, E, S, W) clockwise.
3. Ground Clearance is the height in meters of crown clearance above adjacent ground level.
4. Stem Diameter is the diameter of the stem measured in millimetres at 1.5m from ground level or just above ground level for multi stemmed trees. The diameter may be estimated (e), where access is restricted. An average (a) may be taken for tree groups. A full inspection is always recommended.
5. Protection Multiplier is 12 for single stemmed and 10 for multi-stemmed trees.

6. Protection Radius is a radial distance measured from the trunk centre and is used to calculate the BS RPA.
7. Growth Vitality - Normal growth, Moderate (below normal), Poor (sparse/weak), Dead (dead or dying tree).
8. Structural Condition - Good (no or only minor defects), Fair (remediable defects), Poor - Major defects present or suspected.
9. Landscape Contribution - High (prominent landscape feature), Medium (visible in landscape), Low (secluded/among other trees).
10. B.S. Cat. refers to British Standard 5837:2005 Table 1 category and refers to tree/group quality and value; 'A' - High, 'B' - Moderate, 'C' - Low, 'R' - Remove or very poor quality.
11. Sub Cat refers to the retention criteria values where 1 is Arboricultural, 2 is Landscape and 3 is Cultural including Conservation/ecological, historic and commemorative.
12. Useful Life is the tree's estimated remaining effective contribution in years.

Site: Haymarket, Teddington Studios

Date: November 2013

Surveyor: H. Appleyard

Ref: ts3/haymarket

Tree No.	English Name	Height	Crown Spread	Ground Clearance	Age Class	Stem Diameter	Protection Multiplier	Protection Radius	Growth Vitality	Structural Condition	Landscape Contribution	B.S. Cat	Sub Cat	Useful Life	Observations
T17	False Acacia (Frisia)	10	3 4 4 4	2/W2	Mature	400	12	4.8	Normal	Poor	Medium	C	1	10-20	Cavities with decay (significant) Decay in trunk; broken/hanging branches Large roots in planting bed with suckers
T18	Ash, Common	9	2 2 2 3	4/S5	Mature	500e	12	6.0	Moderate	Poor	Low	U	1,2	<10	Pollard Extensive decay in wound/cavity Ivy covered stump
T19	Plane, London	25	8 7 8 8	5/N5	Mature	1000e	12	12.0	Normal	Good	High	A	1,2	>40	A tree with insignificant defects Reduced in past Root spread restricted by local structures west
T20	Sycamore	17	5 5 5 5	3/N3	Mature	400e	12	4.8	Normal	Good	Low	C	2	20-40	Inspection limited by access Self sown Appears sound; root spread restricted by structures
T21	Lime, Common	25	6 6 6 6	2.5/W4	Mature	700e	12	8.4	Moderate	Good	Medium	B	1,2	20-40	Deadwood throughout crown Reduced in past Root spread restricted west
T22	Chestnut, Horse	23	5 3 5 3	4/N5	Mature	600e	12	7.2	Moderate	Good	Medium	B	2	20-40	Inspection limited by access; seems one-sided Bark wounds (decay entry points) within trunk Root spread restricted west
G23	Sycamore x2	22	5 5 4 5	5/E5	Mature	500	12	6.0	Normal	Good	Low	C	1,2	20-40	Self sown trees on boundary

Notes:

- Height describes the approximate height of the tree in meters from ground level.
- The Crown Spread refers to the crown radius in meters from the stem centre and is shown above on each of the four compass points (i.e. N, E, S, W) clockwise.
- Ground Clearance is the height in meters of crown clearance above adjacent ground level.
- Stem Diameter is the diameter of the stem measured in millimetres at 1.5m from ground level or just above ground level for multi stemmed trees. The diameter may be estimated (e), where access is restricted. An average (a) may be taken for tree groups. A full inspection is always recommended.
- Protection Multiplier is 12 for single stemmed and 10 for multi-stemmed trees.

- Protection Radius is a radial distance measured from the trunk centre and is used to calculate the BS RPA.
- Growth Vitality - Normal growth, Moderate (below normal), Poor (sparse/weak), Dead (dead or dying tree).
- Structural Condition - Good (no or only minor defects), Fair (remediable defects), Poor - Major defects present or suspected.
- Landscape Contribution - High (prominent landscape feature), Medium (visible in landscape), Low (secluded/among other trees).
- B.S. Cat. refers to British Standard 5837:2005 Table 1 category and refers to tree/group quality and value; 'A' - High, 'B' - Moderate, 'C' - Low, 'R' - Remove or very poor quality.
- Sub Cat refers to the retention criteria values where 1 is Arboricultural, 2 is Landscape and 3 is Cultural including Conservation/ecological, historic and commemorative.
- Useful Life is the tree's estimated remaining effective contribution in years.

Site: Haymarket, Teddington Studios

Date: November 2013

Surveyor: H. Appleyard

Ref: ts3/haymarket

Tree No.	English Name	Height	Crown Spread	Ground Clearance	Age Class	Stem Diameter	Protection Multiplier	Protection Radius	Growth Vitality	Structural Condition	Landscape Contribution	B.S. Cat	Sub Cat	Useful Life	Observations
T24	Sycamore	23	7 6 7 4	2.5/W2	Mature	1000	12	12.0	Normal	Good	Medium	B	1,2	20-40	Ivy covered trunk and branches Inspection limited by ivy/access Trunk on boundary; roots restricted west by structures

Notes:

1. Height describes the approximate height of the tree in meters from ground level.
2. The Crown Spread refers to the crown radius in meters from the stem centre and is shown above on each of the four compass points (i.e. N, E, S, W) clockwise.
3. Ground Clearance is the height in meters of crown clearance above adjacent ground level.
4. Stem Diameter is the diameter of the stem measured in millimetres at 1.5m from ground level or just above ground level for multi stemmed trees. The diameter may be estimated (e), where access is restricted. An average (a) may be taken for tree groups. A full inspection is always recommended.
5. Protection Multiplier is 12 for single stemmed and 10 for multi-stemmed trees.

6. Protection Radius is a radial distance measured from the trunk centre and is used to calculate the BS RPA.
7. Growth Vitality - Normal growth, Moderate (below normal), Poor (sparse/weak), Dead (dead or dying tree).
8. Structural Condition - Good (no or only minor defects), Fair (remediable defects), Poor - Major defects present or suspected.
9. Landscape Contribution - High (prominent landscape feature), Medium (visible in landscape), Low (secluded/among other trees).
10. B.S. Cat. refers to British Standard 5837:2005 Table 1 category and refers to tree/group quality and value; 'A' - High, 'B' - Moderate, 'C' - Low, 'R' - Remove or very poor quality.
11. Sub Cat refers to the retention criteria values where 1 is Arboricultural, 2 is Landscape and 3 is Cultural including Conservation/ecological, historic and commemorative.
12. Useful Life is the tree's estimated remaining effective contribution in years.